

# Geo-Seas

## Pan-European infrastructure for management of marine and ocean geological and geophysical data



### 8 – Ends\_And\_Bends\_V2.1.0\_User\_Manual

Organisation name for lead contractor for this deliverable: Ifremer

Project acronym: Geo-Seas

Project full title: Pan-European infrastructure for management of marine and ocean geological and geophysical data

Grant Agreement Number: 238952

Start date of project: 1<sup>st</sup> May 2009

Co-ordinator: Helen Graves



**British  
Geological Survey**  
NATURAL ENVIRONMENT RESEARCH COUNCIL



<b>Deliverable number</b>	<b>Short Title</b>
D8.1	Ends And BendsUser Manual
<b>Long Title</b>	
Ends_And_Bends_V2.05_User_Manual	
<b>Short Description</b>	
This document is the user manual of <b>Ends&amp;Bends</b> , a software used to sample raw navigation (ship routes) and to generate the spatial objects to be included in CDI records to describe the geometries of the observations	
<b>Keywords</b>	
Navigation, sampling, GML, CDI	
<b>Authors / Organisation(s)</b>	<b>Editor / Organisation</b>
Moussat Eric, Ifremer	H. Glaves (NERC-BGS)
<b>File name</b>	
GS_WP8_D8.1_Ends_And_Bends_V2.05_User_Manual.doc	
<b>Deliverable due date</b>	<b>Deliverable submitted date</b>
NA	15 February 2011
<b>Comments</b>	
Not a deliverable. Ends&Bends is a software adapted and proposed by Ifremer to partners to help them to sample their navigation files and to produce the spatial objects in the CDI xml files.	

<b>History</b>				
<b>Version</b>	<b>Author(s)</b>	<b>Status</b>	<b>Date</b>	<b>Comments</b>
V0	Eric Moussat, Ifremer Sophie Bregent	FINAL	15 February 2011	On-line help
V1	Eric Moussat, Ifremer Sophie Bregent	FINAL	26 Nov. 2011	Separate downloadable document
V2	Eric Moussat, Ifremer Sophie Bregent	FINAL	09 April 2013	Update §1.1: correct linux launch script name Update figures 5 &17: improve fields labels
V2.06	Eric Moussat, Ifremer Sophie Bregent	FINAL	21 March 2014	Update §5.5.4: New format ISO 19139
V2.1.0	Eric Moussat, Ifremer Sophie Bregent	FINAL	03 April 2014	Update §5.5.4: File CSR format ISO 19139

<b>Dissemination level</b>		
<b>PU</b>	Public	X
<b>CO</b>	Confidential, for project partners and the European Commission only	

## Executive Summary

**Ends&Bends** is used to generate spatial objects from raw navigation (ship routes) to be included in CDI or CSR records files to describe the geometries of the observations :

- Typical navigation log files record more than one location / 10 seconds (ex : GPS outputs),
- Size of these navigation log files are not practical to be managed or visualized using standard GIS software or services (WMS, WFS and GML)

Navigation log files must be subset, but sub setting must:

- Keep the same geographical shape of the vessel route to allow accurate spatial queries
- Reduce significantly the number of geographical locations to preserve response time (e.g. 1000 points for one month of deep sea navigation, 1000 points for a week of inshore navigation).



## Content

<b>1</b>	<b>RUNNING THE APPLICATION .....</b>	<b>6</b>
1.1	WINDOWS / LINUX .....	6
<b>2</b>	<b>LOADING DATA, GEOGRAPHICAL PROJECTION AND SPLITTING INTO SEGMENTS .....</b>	<b>6</b>
2.1	COORDINATE PROJECTION.....	6
2.2	ACQUISITION STOPS DETECTION.....	6
2.3	PROJECTION CONSTRAINTS .....	6
<b>3</b>	<b>SUBSAMPLING ALGORITHM .....</b>	<b>7</b>
3.1	DEFAULT ALGORITHM .....	7
3.2	OPTIMIZED COMPUTATION .....	8
3.3	SEGMENT CUSTOMIZED COMPUTATION .....	8
<b>4</b>	<b>MAIN WINDOW.....</b>	<b>9</b>
4.1	MAIN WINDOW AREAS .....	9
4.2	INPUT / OUTPUT MANAGEMENT .....	10
4.2.1	<i>Buttons</i> .....	10
4.3	SEGMENTS LIST .....	10
4.3.1	<i>List status</i> .....	11
4.3.2	<i>Handling lines representing a segment</i> .....	12
4.3.3	<i>« Total » line handling</i> .....	12
4.4	OPTIONS .....	13
<b>5</b>	<b>FUNCTIONS ON FILES.....</b>	<b>13</b>
5.1	OPENING A NAVIGATION FILE.....	13
5.1.1	<i>NETCDF NVI Format</i> .....	15
5.1.2	<i>CSV Format</i> .....	16
5.1.3	<i>UKOOA Format</i> .....	17
5.2	DEFAULT COMPUTATION .....	19
5.3	FARTHEST POINT OPTIMIZATION .....	19
5.4	ERROR OPTIMIZATION.....	19
5.5	SAVING PROCESSED DATA .....	19
5.5.1	<i>Ifremer ASCII Format</i> .....	20
5.5.2	<i>ASCII columns format</i> .....	21
5.5.3	<i>WKT format</i> .....	22
5.5.4	<i>GML format</i> .....	23
5.5.5	<i>Shape format</i> .....	24
<b>6</b>	<b>SEGMENT HANDLING.....</b>	<b>24</b>
6.1	SEGMENT VISUALIZATION.....	25
6.2	DEFAULT COMPUTATION .....	29



---

6.3	CUSTOMIZED COMPUTATION .....	29
<b>7</b>	<b>OPTIONS .....</b>	<b>29</b>
7.1	THRESHOLDS.....	30
7.2	PROJECTION.....	31
7.3	VERY LONG DISTANCE .....	32

## 1 Running the application

The application can be executed from the command line as follow, either on Windows or Linux.

### 1.1 Windows / Linux

The application can be launched from the DOS / Linux command line terminal when located in the installation folder :

- in English : `java -jar EndsAndBends.jar -nl en`
- in French : `java -jar EndsAndBends.jar -nlfr`

DOS or SHELL scripts `LaunchEndsAndBendsEnglishRelease` (windows), `LaunchEndsAndBendsFrenchRelease` windows) and `EAB.sh` (linux), located in the installation folder, simply runs the application by double right-clicking from your file browser or by typing « `LaunchEndsAndBendsEnglishRelease.bat` » or « `./EAB.sh` » in a DOS / Linux command line terminal when positioned in the installation folder.

Carefully check that you have the proper permissions to execute those files.

## 2 Loading data, geographical projection and splitting into segments

### 2.1 Coordinate projection

The algorithm detailed below computes distances from geographical coordinates (angles). In order to do so, all the geographical coordinates must be projected on a plane. However, the original geographical coordinates in latitudes and longitudes are preserved and are never recomputed from planar coordinates. Projected coordinates are only used to compute distances between points, hence there is no precision loss when writing output data results.

### 2.2 Acquisition stops detection

Multibeam echosounder navigation files contain data harvested during a whole survey. Sometimes the positioning data stops which entails gaps in the navigation outline. Consequently, once the navigation file is loaded, data survey are splitted into *segments*. Each segment contains contiguous data. The splitting process is based on two information : time and distance. A 10 minutes maximum gap (and the corresponding distance for an average speed of 10 knots) is used by default.

### 2.3 Projection constraints

The only geographical projection provided in the application is the Gauss-Krueger projection. It is *Ends&Bends* basic projection. The limitation of this projection lies in the distances deformation for very

long distances. Projected points in the same reference system must not be separated by more than  $5^\circ$  in latitude. This is an indicative limit, the application permits modifying it. In order to project all points without drawbacks, the application splits segments which are too long. This operation is performed just after the acquisition stops detection, when loading the data.


### 3 Subsampling algorithm

#### 3.1 Default algorithm

The implemented algorithm can be summed up in three steps :

- First, the two ends of a segment are chosen,
- Then we add the other points one by one choosing first the farthest from the polyline going through the already selected points.
- The adding process stops when the global error reaches the desired level of error.

The operating principle is described by the following picture.



In the original basic program *Ends&Bends* (J. Bolotosky and K. Koschyk, 2000) , the global error between the real and the simplified outline is estimated by the mean of the squared distance between the original points and the simplified outline, divided by the total length of the real outline. Thanks to this error, the software defines 5 models each corresponding to a particular level of error ( $10^{-1}$  for the model 1, to  $10^{-5}$  for the model 5).

This algorithm has been improved to better take into account the 999 points limit. The « models » technique drawback is that those models do not depend of the number of obtained points : it often happens that a model has much less than 999 points when the next one has much more than that and finally the user has to select the less accurate model in order to respect the 999 points limit. The algorithm works adding points one by one, so one can decide to stop it using any criterion.

The implemented algorithm in the new application *Ends&Bends* uses this feature to compute intermediate models which have a multiple of 999 points. The result is no longer limited to 5 models and can contain up to 10.

Two criteria are then used to define a model :

- Either the error falls under a threshold in  $10^{-n}$ ,
- Or the number of point is less than or equal to a multiple of 999.

### 3.2 Optimized computation

Eventually, an ultimate algorithm has been implemented, still taking advantages of the fact that points are adding one by one and changing the stop adding criterion. This computation is intended for taking into account the 999 points limit on the whole survey and not only on one segment. To do so, the algorithm process all the segments at the same time. At each iteration it determines which segment has to be optimized and then add a point to this segment. The algorithm stops when the total number of points reaches 999.

There are two ways to choose which segment has to be optimized :

- either we choose the one which has the most distant point from the simplified outline : it is the ***Farthest point optimization***
- or we choose the one which has the highest global error : it is the ***Error optimization***


### 3.3 Segment customized computation

To tune with more accuracy the subsampling on a segment, another algorithm has been implemented : the operator is asked to chose the number of points he wants to obtain. In this case, the algorithm is unchanged, but only one model is computed. This model is associated to the chosen segment and contains the exact number of points asked.



## 4 Main window

### 4.1 Main window areas



**Figure 1 Main window**


The main window consists in two areas :

- Left area : buttons which permit global handling of a navigation file.  
The buttons in the " Survey Process" area are always enabled, they permit global operations on the navigation file. The buttons in the " Segment Process" area are only enabled when a segment is selected, they permit operations on one segment.
- Right Area : a table which contains a list of loaded segments from a navigation file.





## 4.2 Input / Output management

### 4.2.1 Buttons



Source area :

	<p><i>Open a navigation file</i></p> <p>Permits loading into memory a new navigation file. Previously loaded data are lost.</p>
---	---


Survey process area :

	<p><i>Show survey</i></p> <p>Permits to show all the survey outline.</p>
	<p><i>Default Computation</i></p> <p>Performs the default computation model for all segments (<a href="#">details</a>).</p>
	<p><i>Farthest point optimization</i></p> <p>Performs a model computation for each segment, in order to get exactly 999 total points with distance criterion (<a href="#">details</a>).</p>
	<p><i>Error optimization</i></p> <p>Performs a model computation for each segment, in order to get exactly 999 total points with global error criterion (<a href="#">details</a>).</p>

Segment process area :

	<p><i>Default Computation</i></p> <p>Performs the default computation model on the selected segment.</p>
	<p><i>Customized computation</i></p> <p>Performs a computation on the selected segment we can customized by changing the number of points (<a href="#">details</a>).</p>

Target area :

	<p><i>Save results</i></p> <p>Save subsampled data.</p>
---	---

## 4.3 Segments list

The table contains the list of segments which are loaded into memory.

### 4.3.1 List status

When running the application, this list comes empty. After having loaded a file navigation, the columns are filled.

In this status, the list appears as follow :

N°	Point Nb	Model	Point Nb	Error
1	30525	aucun	30525	0.0
2	99206	aucun	99206	0.0
3	20353	aucun	20353	0.0
4	4070	aucun	4070	0.0
total	154154		154154	0.0

The table "Result of initial segment processing" is empty.

The table appears as follow :

Optimization	Model	Point Nb	Error

After the default computation on the survey, the other columns are filled.

In this status, the list appears as follow :

N°	Point Nb	Model	Point Nb	Error
1	30525	999 points	999	1.1058908091126998E-5
2	99206	999 points	999	1.5087166750631474E-5
3	20353	999 points	999	1.0953357554444921E-5
4	4070	999 points	999	5.8616022094940165E-6
total	154154		3996	1.0740258651424354E-5

The first line of the table "Result of initial segment processing" is filled.

In this status, the table appears as follow :

Optimization	Model	Point Nb	Error
Default optimization	999 points	999	1.5087166750631474E-5

After the farthest point optimization the columns are filled as follow :

N°	Point Nb	Model	Point Nb	Error
1	30525	dist optim	213	1.0845150725059569E-4
2	99206	dist optim	493	3.319494499664613E-5
3	20353	dist optim	222	1.0335791232553988E-4
4	4070	dist optim	71	3.7712987175932605E-4
total	154154		999	1.5553355908302693E-4

In the example above, the 4 first lines of the segment list represent each a segment. The last line represent the total number of points and the total error on all segments.

Then the second line of the table "Result of initial segment processing" is filled. In this status, the table appears as follow :

Optimization	Model	Point Nb	Error
Default optimization	999 points	999	1.5087166750631474E-5
Farthest Point opti...	dist optim	493	3.319494499664613E-5

### 4.3.2 Handling lines representing a segment

The columns have the following meaning :

N°	segment identification number
Point Nb	segment number of points before optimization
Model	selected model name (see combo list use below)
Point Nb	optimized segment number of points
Error	error due to segment optimization

Once an optimization has been computed either on the survey or on a segment, up to 10 models are available on a segment. In this case, a combo list displaying the computed models appears through a mouse clic on the frame « model ». The combo list contains the model names, see the following chapters.

N°	Point Nb	Model	Point Nb	Error
1	30525	999 points	999	1.1058908091126998E-5
2	99206	err < 10-2	999	1.5087166750631474E-5
3	20353	err < 10-3	999	1.0953357554444921E-5
4	4070	err < 10-4	999	5.8616022094940165E-6
total	154154	999 points	3996	1.0740258651424354E-5
		err < 10-5		
		1998 points		
		2997 points		
		3996 points		

Figure 2 Models list

### 4.3.3 « Total » line handling

The columns have the following meaning :

N°	segment identification number
Point Nb	total number of points in the navigation file
Model	usually empty, except when a global model is chosen (see combo list use below)
Point Nb	optimized total number of points, this value must be less than or equal to 999 so that the output result file be valid.
Error	error sum on every segment.

The "model" frame of the total line is usually empty. A combo list appears on a mouse clic, suggesting criteria on the error. This list permits defining segments default model.

N°	Point Nb	Model	Point Nb	Error
1	30525	999 points	999	1.1058908091126998E-5
2	99206	999 points	999	1.5087166750631474E-5
3	20353	999 points	999	1.0953357554444921E-5
4	4070	999 points	999	5.8616022094940165E-6
total	154154		3996	1.0740258651424354E-5
		err < 10-3		
		err < 10-4		
		err < 10-5		

If an error level is selected, the application will choose amongst available models, for each segment, the first with which the error is less than the selected level. If none of them fits, the segment has no selected models and the application considers the segment not optimized.

## 4.4 Options

Options
  
[Threshold] Time gap: 10 min Max point nb: 999
  
[Projection] Gauss-Krueger Vertical
  
[Distance] Max angle: 11.0° Min angle: 10.0°




Figure 3 Options area

There is an Options area at the top of the window. This area is composed of :

- A text which sums up the selected threshold, projection and distance.
- An « Options... » button, which opens the Options dialog window, described in paragraph 7.

## 5 Functions on files

### 5.1 Opening a navigation file

To load a navigation file clic on the button "Open navigation file". The application permit using a parameter file. If you don't choose to use any parameter file the window opens on the NETCDF NVI format.

***When this function is called, the application flushes all the data that would have been previously loaded into memory.***

When data are loaded into memory, the application performs the following operations :

- Projection of the points (see details in paragraph 2)
- The whole survey is divided into continuous navigation segments (see details in paragraph 2)
- Segments which are too large for the selected projection are also divided into sub-segments (see details in paragraph 2)

As these operations use the selected projection, like other options, data loaded into memory must be updated when the projection is changed.

Once the file is properly loaded, the application displays the list of segments from the navigation file in the central table.

The detail of split causes is available in the endsAndBends.log file, in the root directory installation of Ends&Bends. The log lists each segment with information on split type for begin and end of segment.

Types are:


- ABSOLUTE\_START: start of the hole trajectory (first point of first trajectory segment)
- TIME\_GAP: TIME between this segment and next or previous one is greater the TIME threshold
- DISTANCE\_GAP: DISTANCE between this segment and next one is greater the DISTANCE threshold
- PROJECTION\_SPLIT: an artificial cut has been forced because the segment area was too big for projection
- ABSOLUTE\_END: end of the hole trajectory (last point of last trajectory segment)

Example:

```
-----
split summary for file dummy.nvi
-----

2013-04-09 15:49:16,609          INFO  [MainForm] seg. no 0 127621
pts ABSOLUTE_START - TIME_GAP - LON: -70.01776079999999 - LAT:
18.424972999999998
2013-04-09 15:49:16,609          INFO  [MainForm] seg. no 1 106212
pts TIME_GAP - PROJECTION_SPLIT - LON: -72.3505938 - LAT: 18.55417755
2013-04-09 15:49:16,609          INFO  [MainForm] seg. no 2 8577
pts PROJECTION_SPLIT - ABSOLUTE_END - LON: -65.1611712 - LAT: 15.66506415
```


The trajectory into the dummy.nvi file has been splitted into 3 segments :



In the "Input navigation file" window we have the choice between two formats :

- NETCDF NVI Format
- CSV

#### 5.1.1 NETCDF NVI Format




**Figure 4 Input navigation file window, netCDF NVI format**

The window consists in two areas :

- in the first one we can filter the data between two dates

- the second one forces the splitting specifying start and stop dates

### 5.1.2 CSV Format



**Input navigation file**

Type: CSV

**Filter**

☐ Specify temporal range

Start date:  MM/dd/yyyy  HH:mm:ss

End date:  MM/dd/yyyy  HH:mm:ss

First data line number:


Last data line number:

☐ Valid when column:  equal

☐ Ignore date ☐ Tick the box if date and time are in same date format field

Delimiter used: ;

	Column number	Format
Date	<input type="text"/>	yyMMdd
Time	<input type="text"/>	HHmmss.S
Latitude	<input type="text"/>	+DD MM.mm
Longitude	<input type="text"/>	+DDD MM.mm

Input navigation file:  

Cancel OK

**Figure 5**Input navigation file window, CSV format


The window consists in two areas :

- in the first one we can filter the data between two dates
- the second one specifies the input file format




### 5.1.3 UKOOA Format

Date/time values are not read in the UKOOA file if present. Thus, you **MUST** use gap limit using distance in the Thresholds Options. If a gap limit using time is chosen, the following error message will be displayed:



Open a UKOOA file:

1. Check if thresholds is set to "distance" in the Options panel (see 7.1)
2. choose the UKOOA file with the browse button at the bottom of the window
3. choose angular unit: Grades or Degrees (default is Degrees)



Type: UKOOA P1-90

Filter

☐ Specify temporal range

Start date:  MM/dd/yyyy  HH:mm:ss

End date:  MM/dd/yyyy  HH:mm:ss

Angular Unit

☐ Grades ☒ Degrees

☐ Force splitting file in profiles

Segment start date	Segment end date
--------------------	------------------

Buttons: Add, Insert, Delete, Edit

Input navigation file: C:\Documents and Settings\jdoe\ukooaFiles\ABCD1\_L001\UKOOA.txt

Buttons: Cancel, OK

Figure 6 Input navigation file window, UKOOA format

## 5.2 Default computation

This function uses the default algorithm described in paragraph 3.1. It consists in computing several models per segment, at most ten. For each segment, a default model is selected. Two criteria are taken into account to choose the default model :

- The first model which contains the maximum number of points in a summary file.
- The first model whose error is less than  $10^{-5}$ .

After this computation, the segment list is updated. As each segment contains several models, the combo lists in the "model" column are enabled for each segment.

The performed computation doesn't take into account the maximum number of point for the whole survey, so by default the total number of points is most of the time greater than the acceptable summary file limit, except when the central table contains only one segment.

## 5.3 Farthest point optimization

This function uses the optimized algorithm described ion paragraph 3.2, using the longest distance as a criterion to choose the segment which has to be optimized.

For each segment, only one model is computed, it is named "optimdist".After this computation, the segment list is updated. As each segment contains only one model, the combo lists in the "model" column are disabled for each segment.

## 5.4 Error optimization

This function uses the optimized algorithm described in paragraph 3.2, using the error as a criterion to choose the segment which has to be optimized.

For each segment, only one model is computed, it is named "optim error".After this computation, the segment list is updated. As each segment contains only one model, the combo lists in the "model" column are disabled for each segment.

## 5.5 Saving processed data


This function exports a summary file from the selected models on each segment of the central table. If no model is selected, the original segment is used. The application displays a warning if the number of total point is greater than the acceptable summary file limit. Then we have the possibility to load a file paramater. If you don't choose to load any parameter file the window opens on the Ifremer ASCII format.

In the "Output navigation file" window we have to choose between five formats :

- Ifremer ASCII format
- ASCII columns format
- WKT format
- GML format
- Shape format

When all parameters are filled you must give a file name and the data are exported. The geographical coordinates written in the summary file are those which were initially read in the navigation file, they didn't go through any transformation.

### 5.5.1 Ifremer ASCII Format




The screenshot shows a dialog box titled "Output navigation file" with a close button (X) in the top right corner. The "Type" dropdown menu is set to "Ifremer ASCII format (P50)". Below this, there are two radio buttons: "Survey" (selected) and "Data". To the right of these is a checkbox labeled "Write seconds", which is currently unchecked. Below the radio buttons are five text input fields, each with a label and a character limit: "Operator name (20 char.)", "Comment (8 char.)", "Survey identifier (8 char.)", "Survey title (25 char.)", and "Platform name (25 char.)". At the bottom of the dialog, there is a section labeled "Choose file for results" with a text input field and a file selection icon (a folder with a magnifying glass). At the very bottom right are two buttons: "Cancel" and "OK".

**Figure 7 Output navigation file window, IfremerAscii format**

Here, one can edit the necessary information to fill the summary file headers.

## 5.5.2 ASCII columns format



The dialog box is titled "Output navigation file" and has a close button (X) in the top right corner. It contains the following fields and controls:


- Type:** A dropdown menu set to "ASCII columns format".
- Time to apply:** A numeric input field with a spinner, set to "0".
- Join date and time parameters:** An unchecked checkbox.
- Column number and Format table:**

	Column number	Format
Date	<input type="text"/>	yyMMdd
Time	<input type="text"/>	HHmmss.S
Latitude	<input type="text"/>	+DD MM.mm
Longitude	<input type="text"/>	+DDD MM.mm
- Start/End Indicator:** Two text input fields, one for "Start Indicator" and one for "End Indicator".
- Delimiter used:** A text input field.
- Choose file for results:** A text input field with a file explorer icon on the right.
- Buttons:** "Cancel" and "OK" buttons at the bottom right.

**Figure 8**Output navigation file window, Ascii columns format

Here, one can specify his own output ASCII format. All fields are mandatory in this window

### 5.5.3 WKT format

A screenshot of a software dialog box titled "Output navigation file". The dialog has a blue title bar with a close button (X) in the top right corner. Inside the dialog, there is a "Type" dropdown menu set to "WKT format". Below this, there is a section labeled "Resolution: decimals size" with a text input field containing the number "0" and a small up/down arrow button. At the bottom of the dialog, there is a label "Choose file for results" above a text input field. To the right of the input field is a small icon of a document with a pencil. At the bottom right of the dialog are two buttons: "Cancel" and "OK".

Type: WKT format


Resolution: decimals size: 0

Choose file for results

Cancel OK

Figure 9 Output navigation file window, WKT format

## 5.5.4 GML format



**Figure 10**Output navigation file window, GML format

There are two ways to generate GML information :

- GeoBndBox and multicurve information in geoEle tags are written in an XML file.
- GeoBndBox and multicurve information in geoEle tags are updated in a mikado file (CDI or CSR).
- EndsAndBends expects a mikado file ISO 19139. To update old CDIs or CSRs, please use Mikado version 3.3.3 or later.

### 5.5.5 Shape format




Figure 11Output navigation file window, shape format


## 6 Segment handling

Once a segment is selected in the central table, the buttons from the Segment process area are available.



## 6.1 Segment visualization

When selecting a line in the central table a "Segment visualization" window appears.




**Figure 12 Segment visualization window**

When using the "Show survey" button, another "Survey visualization" window appears underneath. In this window the survey appears in black and the selected segment in green.


Meridians are also represented in blue.

Meridians are also represented in blue.




**Figure 13**Survey visualization window

After a computation, thanks to these windows, projected geographical coordinates from the initial navigation file are displayed in black while the coordinates from the models are displayed in red with crosses.



**Figure 14**Survey visualization after computation



**Figure 15 Survey visualization scale**

A text displayed at the bottom of the window gives a geographical scale of the outline. This scale is the angular distance between two meridians.


When these windows open, the zoom is automatically chosen so that the segment or survey fits the window size. Buttons and scrollbars at the bottom of the window enable the user to display any area.

Buttons have the following properties :

<b>Zoom +</b>	increase the zoom so that the outline is scaled up
<b>Zoom -</b>	decrease the zoom so that the outline is scaled down
<b>Zoom on selection</b>	define an area to zoom on
<b>Show all</b>	get back to a proper scale so that the whole segment or survey fits the visualization window

**Tableau 1 Survey visualization window buttons**

When the « Zoom on selection » button is enabled, the mouse cursor is in a selection zone mode on the visualization window, that is to say one can define a rectangle moving the mouse while left-click and dragging. The other buttons are disabled.



**Figure16 Survey visualization zoom**

## 6.2 Default computation

This function performs the computation described in paragraph 3.1 on the selected segment.

## 6.3 Customized computation

This function performs the computation described in paragraph 3.3 on the selected segment. A dialog box is displayed to fill in the number of points desired at the optimization outcome. Only one model is computed, it is named "custom".

Once this computation performed, the segment list is updated. As each segment has only one model, the combo lists in the "model" column are disabled for each segment.

## 7 Options

Ends & Bends computations and output summary files are widely configurable. The « Options » button opens the option window with three tabs, each one tuning a different aspect of the application.

<b>Thresholds</b>	It defines the different thresholds used when loading an input file : the time gap limit for interrupt segment detection and the maximum number of points allowed in a summary file.
<b>Projection</b>	One can choose the projection used and the kind of distance computed.
<b>Very long distance</b>	It defines the maximum angular distances according to very extended segments issue.


**Tableau 2 options buttons**

## 7.1 Thresholds

Here, one can tune the thresholds used during the input file loading and the computations.

Two thresholds are considered :

- The first one is the time gap limit above which we want to consider that the navigation has been interrupted. It is used when loading a navigation file in order to split the data into continuous segments. By default, this threshold type is "time" and is set to 10 minutes.
- The second threshold is the maximum number of positions a summary file can hold. It is used during the default or optimized computation and its default value is 999.



**Computation options**

Thresholds Projection Very long distance

Select the option and put the minimum interval between two consecutive points considered as a gap in data recording.

☒ time (minutes) (for time series only) 10

☐ distance (meters) 3,000

The gap is used to determine point series without record interrupt (segments) to sample.

---

Max point number sampled in the summary file.

999

The max points number indicates from when the sampling must stop.

Cancel OK

**Figure 17 Computation options - Thresholds**


## 7.2 Projection

Here, one can choose the projection being used when loading a navigation file. For now, the only projection implemented is the Gauss-Krueger.

The kind of distance chosen during the computation can also be chosen. This distance is measured between a point and a line.

Two kinds of distances are available :

1. The Vertical distance is computed along the y-axis between a point and the optimized line.
2. The Orthogonal distance is computed between a point and a line on an orthogonal segment to this line.



**Figure 18 Computation options - Projection**


### 7.3 Very long distance

Here, one can define specific parameters for Gauss-Krueger projection. These parameters set the maximum longitudinal extension that can handle the projection. In order to be more convenient, this feature lies in two parameters :

- The angular distance a unique segment can reach without being splitted when loading is set by default to 11°.
- The angular distance from which a segment exceeding the first threshold would have been splitted is set by default to 10°.

This method aims at avoiding the creation of very small segments. For example, with the default values, a segment whose maximum extension is 11.05° will be splitted into two segments of 10° and 1.05°.





**Figure 19**Computation options - Very long distance

## Annex A. References

This is section mandatory for all deliverables

[1] This is the Style “Geo-Seas Reference”. Just press enter to create the next one.

## Annex B. Figures and Tables

### B.1. List of Figures

FIGURE 1 MAIN WINDOW	9
FIGURE 2 MODELS LIST	12
FIGURE 3 OPTIONS AREA	13
FIGURE 4 INPUT NAVIGATION FILE WINDOW, NETCDF NVI FORMAT	15
FIGURE 5 INPUT NAVIGATION FILE WINDOW, CSV FORMAT	16
FIGURE 6 INPUT NAVIGATION FILE WINDOW, UKOOA FORMAT	18
FIGURE 7 OUTPUT NAVIGATION FILE WINDOW, IFREMERASCII FORMAT	20
FIGURE 8 OUTPUT NAVIGATION FILE WINDOW, ASCII COLUMNS FORMAT	21
FIGURE 9 OUTPUT NAVIGATION FILE WINDOW, WKT FORMAT	22
FIGURE 10 OUTPUT NAVIGATION FILE WINDOW, GML FORMAT	23
FIGURE 11 OUTPUT NAVIGATION FILE WINDOW, SHAPE FORMAT	24
FIGURE 12 SEGMENT VISUALIZATION WINDOW	25
FIGURE 13 SURVEY VISUALIZATION WINDOW	26
FIGURE 14 SURVEY VISUALIZATION AFTER COMPUTATION	27
FIGURE 15 SURVEY VISUALIZATION SCALE	28
FIGURE 16 SURVEY VISUALIZATION ZOOM	29
FIGURE 17 COMPUTATION OPTIONS - THRESHOLDS	31
FIGURE 18 COMPUTATION OPTIONS - PROJECTION	32
FIGURE 19 COMPUTATION OPTIONS - VERY LONG DISTANCE	33

### B.2. List of Tables

TABLEAU 1 SURVEY VISUALIZATION WINDOW BUTTONS	28
TABLEAU 3 OPTIONS BUTTONS	30

## Annex C. Terminology

This annex is also mandatory

Term	Definition
CDI	The Common Data Index designates the catalogues of observation data sets of the Geo-Seas ( <a href="http://www.geo-seas.eu/">www.geo-seas.eu/</a> ) and SeaDataNet ( <a href="http://www.seadatanet.org/">http://www.seadatanet.org/</a> ) infrastructures
CSV	Comma-Separated Values : file format to store tabular data (numbers and text) in plain-text form
GIS	Geographic Information System
GML	The Geography Markup Language (GML) is the XML grammar defined by the Open Geospatial Consortium (OGC)

	to express geographical features
GPS	Global Positioning System
NetCDF	Network Common Data Form : set of software libraries and self-describing, machine-independent data formats that support the creation, access, and sharing of array-oriented scientific data. The project homepage is hosted by the Unidata program at the <u>University Corporation for Atmospheric Research</u> (UCAR) <a href="http://www.unidata.ucar.edu/software/netcdf/">http://www.unidata.ucar.edu/software/netcdf/</a>
NetCDF NVI	A NetCDFifremer navigation file format
Shape	Geospatial vector data format for geographic information systems (GIS) software
UKOOA format	A format for the exchange of positioning data originally defined by the UK Offshore Operators Association : <a href="http://www.ogp.org.uk/publications/geomatics-committee/p-formats-for-the-exchange-of-positioning-data/">http://www.ogp.org.uk/publications/geomatics-committee/p-formats-for-the-exchange-of-positioning-data/</a>
WMS	Web Map Service : an OGC standard protocol for serving georeferenced map images over the Internet that are generated by a map server using data from a GIS database
WFS	Web Feature Service : an OGC interface allowing requests for geographical features across the web using platform-independent calls
WKT	Well-Known Text :a text mark-up languagefor representing vectorgeometryobjects on a map, spatial reference systems of spatial objects and transformations between spatial reference systems

## 8 Log

A log file named endsAndBends.log is available in the Ends&Bends root installation directory.